

Theory and Decisions | Tools and Options Printline or Records Mode | Design and Objects | Masking and Font Change Projects | Testing and Viewing | Repaginator | FTSplitDef

FormTrap Repaginator

Overview

Loading a Sample Data

Entry

New Entry

Header Area

Footer Area

Data Area

Rules

Properties

Evaluation Order of Entries

▶ Evaluation Order of Areas

Delete an Entry, Area or Rule

■ Tools

Running Repaginator from a Command Line

Properties



Once you have finished creating the areas in the entry, you can modify the entry and area

Entry Properties

To modify the properties of the selected entry:

Select the entry in the **Areas window** and click the **Properties tool** button on the toolbar, or choose **Entry** from the **Edit** menu.
 The **Entry** dialog box opens.

- Change the Name of the entry which should represent that being processed.
- To insert text at the beginning of each document, enter the string in the Prepend with text box
- To insert text at the end of each document, enter the string in the **Append with**text box. This is used to insert ##NEWDOC# which resets the page number for
 multiple documents from one file. The next (Form Feed) option is not required
 after a ##NEWDOC# command. To insert another document behind this one use these commands (typically used to insert a one-page terms and conditions document behind an invoice or PO):
 - o ##F#<form-name># where form-name is the name of the required form
 - o 0 (record mode) or just some data such as "base page" (print line mode)

- To insert a form feed at the end of each document, tick the Form feed at the end checkbox.
- Click **OK** to save the changes.



Ton

Area Properties

Once the areas have been defined, you can modify their properties, including height


In the data area(s), you also have the option to suppress the output. This is the normal approach to repagination, suppress all that you do NOT want, leaving all of the remaining non-blank lines as the "keepers".

To modify the properties of the selected area:

- Select the area to modify in the Areas window and click the Properties tool
 - button on the toolbar or choose **Properties** from the **Edit** menu.

- The **Area** dialog opens.
 Enter the new **Height** (number of lines).
 Select the properties of the rules defined on the selected area:

 - All must succeed As stated.
 Any can succeed At least one of the rules defined on the selected must succeed to identify this area.
- Suppress output option applies only to data areas. To suppress the output of the data area tick the **Suppress output** checkbox. The data area icon in the **Areas window** changes to show it will be suppressed in the output.
- Click OK to save the changes.



Disclaimer | Home | About Us | News
Products | Customer Area | Free Trial | Success Stories | Contact Us

Copyright © 1995 - 2010 TCG Information Systems Pty. Ltd. All rights reserved.